


**Environmental Quality:
Monitoring and Analysis
Prof. Ravi Krishna
Department of Chemical Engineering
Indian Institute of Technology-Madras**

**Lecture No. 32
Vapour – Part 3**

(Refer Slide Time: 00:11)



So, while coming back to our thermal desorption what is done is the following. So, you take your sample in a tube, you attach it to a pump in the usual way and then this tube is brought to what is called now called as an automated thermal desorption unit. It is an accessory to a GC, it is kept before a GC. It doesn't have to be a GC, it can be anything, any analytical instrument it is an accessory before analytical instrument the processing accessory.

And so, this thermal desorption tube is placed in a heated chamber or jacket or whatever and it needs to go to an analytical instrument. So, let us say it needs to go to a GC for example, assume that it is going to a GC. So, this tube when you heat it to a very high temperature what will happen is, it will all come out the desorption will happen, but it can't stay there it has to be taken out quickly. So, what we do is flash desorption.

Flash desorption means it is very quick, it happens very quickly, the temperature shoots up very fast and everything comes off in one shot. If you are increasing temperature slowly little by little, it will come the adsorption as of changing slowly but you want all of it to come at once. Why do you want all of it to come at once? Because when you are sending gas here to sweep everything out, you want the volume of the sample to be as small as possible.

Because now you are going to inject it into GC you, if you recall the GC or injection is very quick, we are injecting a pulse there. So, we want it to be as close as possible to a pulse. Otherwise, separations will have a problem in sample injection, your sample chromatography, retention time will change and all that so, it is very difficult to manage it, so to the extent possible they try to do this as quickly as possible. It is a very interesting system.

You know, a lot of chemical engineering concepts go into this and how quickly you can convert this into a pulse sample. So there is usually a sweep gas, essentially that's what it does, it sweeps it, whatever is now desorb it just takes it flushes it out. This is usually the carrier gas that is used in the GC, you don't want something else mixing with it, you are using argon or helium or nitrogen there, you use the same thing here. So it is usually the carrier gas in the GC and it goes into the GC, how can it go into the GC?

GC has what is called as a sample loop. The sample loop is the holding place for the sample, you are sending in certain concentration. And you would like the sample loop to hold all the sample that you are bringing. So this is important, because what you measure in the GC depends on what you are injecting and what you are desorbing. It has to be in a finite well defined volume so that you know what that volume is, you know what the sample volume is, otherwise you don't know what you are injecting what is coming out and all this is a big mess. So, this is all carefully calibrated and done. So the sample loop will allow you to keep this in place, ok, let's not get into sample loop, you can go and read about it, you can type GC sample loops and the schematics for that comes, very neat system. There are 6 ports and a sample loop essentially will go in and there is a small loop, this is a loop, this is a certain volume of this loop depending on this is the injection volume, you can have it as big as you want 100 micrometers to 1 ml whatever. And the other part

of the system, there is a GC gas coming in, this is a carrier gas coming in from another cylinder and it goes to the GC somewhere.


What happens is when you switch is a certain configuration of this where it is called as a loading cycle when you switch, the GC gas will take the sample loop and go to GC. So that is what will happen. I am not drawing it here but there is called as the rotary this thing. So, I will not draw it here, we will just leave it like this, go and read about sample loops. I will put it up out of the context here. So, it is possible to do it and people do it and calibration now has to be done on this basis.

When you are doing 80D, you have to calibrate like this, which means that I have to inject a known concentration of gas, the calibration now becomes very very difficult. Because now we are if calibrating a concentration, you have to do it on the context of this one and also you have to do some adjustments to your calibration. If you want to use an older calibration you have to make sure that it corresponds to that and all that, so separate.

But the idea here is you are now eliminating one processing step, manual processing step, you are automating everything, this is especially good for what is called as volatile organic compounds or VOCs basically which compounds which have high Henry's high volatility high vapor pressure high very low K_{ow} there are various things like Benzene, Toulene all those things which classify under VOCs.

There is another application of this kind of system when you are doing analysis of VOCs in water. Suppose you want to analyze benzene, the Henry's constant of benzene in water is very high. So, when you are doing all that extraction, the moment you take sample, sample is constantly going out, the chance of losses are quite high so people don't do liquid-liquid extraction for VOCs.

(Refer Slide Time: 07:01)



They use another technique called as purge and trap, you will see this in the methods that you are using. This is a sample processing accessory. What this does is it takes the water sample directly and it purges it. You purge with nitrogen, nitrogen gas is released. When nitrogen gas is flushing out all the volatiles in the system you are stripping the water. This is the water sample water + analyte and analyte + nitrogen both of them are coming out. Again nitrogen or anything helium or argon whatever you are using.


Basically, you are extracting but you are not extracting using solvent, you are extracting using a gas, a vapor phase because that is favorable this is a volatile component anyways coming out. Now at this point this becomes like a vapor sample, air sample. What do you do? You put a small thermal desorption tube here, we are doing the adsorption here, it goes in and sits here this is trap, this is the purge we trap it until all of it is purged. You project it for 15 minutes, 20 minutes, half an hour whatever time you determine that this is a mass transfer problem.

You know how long you need to purge it depends on what is the concentration, what is the flow rate of the bubbles and what is the size of bubbles and all that. We just purge everything and then you go and trap it. Once you trap it, trapping cycle is done then you do what we did in the thermal desorption, you do thermal desorption after that and then it goes to a GC or GCMS or whatever through a sampling loop again, it has to go through a sample loop to do this. So the accessories which are very useful in analyzing this.

So all of these are directed towards only one thing, all the accessories as we are trying to increase our confidence in our analysis, quality control and quality analysis is the focus in most of these methodologies that are developed for these kind of things. So, we will just go over quickly.


(Refer Slide Time: 09:32)


Passive Samplers



- A) No flow through
- B) Equilibrium Based
- C) Adsorbent or Plastic film
- D) Extraction after sampling
- E) Long sampling times

Source: skcinc






So, this is the other type of samples. This is something called as passive sampler, this is a new thing, and not a standard method, this is still under development. So, this is an equilibrium based sampler, which means that in all the other things what we have done is we take a sample of air, we know what's the volume of air and we extract whatever is there and that we exactly get concentration mass by volume.

Here, some cases for example, if you want to take ambient air samples in the way we described just now, what is called as active sampling. Active sampling is where actively I am pulling in a certain volume of air. But the problem is I need a pump, sometimes I need electricity, sometimes I need somebody there and some things may be stolen and all that so the logistical problems are there.

So, what people have come up with is what is called a passive sampler, you put hundreds of this passive samplers, which means it is just a some matrix, some substrate and it comes to equilibrium

with the ambient air or ambient water, wherever you put it in water, you put it in air. And this is one such thing. So, it again works on equilibrium which means, at the end of some period, you take it out, you assume you find out if it is in equilibrium with something else with the ambient air and you extract. All the work is in a laboratory in a processing facility. But there is nothing else in the field. You can have hundreds of these things, bring it back to the lab and you find out what is the concentration so, essentially what we are doing is in this case.

(Refer Slide Time: 11:25)



we are using a partition constant we are using some other material we are using some substrate, some solid. So we have a partition constant here, just K_{A42} or K_{A41} if we know this number this equals W_{A4} divided by ρ_{A2} or W_{A4} divided by ρ_{A1} , we measure this we know this we can calculate this number. This is very useful for getting long term, average concentrations of materials. And it is also cheap when it is easier for a for people to find.

So, people use this to find out especially when the flow is all not very, you know, difficult to manage it and all that. Conditions will change no sir. It's in equilibrium so it is long term average, so you cannot use it like a daily average and all that. It is a long term average it's there it's useful for processes which are the interpretation of this is let say for example, you have a lake or a river or an ocean. It is there for a long time and things are not going to change over 2 days or 3 days.

This is a long term process. Similarly, with atmosphere also. So atmosphere your long term average exposure average you are talking about 30 years, 40 years, 50 years and all that. So, things don't change very rapidly what we are talking about is something pollutant is entering mixing. And this pattern stays for a while until you make a drastic change. Suppose I all of a sudden if I say I am removing all vehicles today, it will take about a month for everything to reset to go to some other value, because there is already some concentration that might get for it to get flushed out. So, this is an this is good for those kind of you can't use this to suggest that is the other end right we are on one hand we are saying we do not we are not happy with 24 hour averages. We want to go real time. This is the other extreme, but this is sometimes useful because it is very cheap to do outside. You see the logistically, it is very difficult to go and install something, especially a place like this people will come and steal components and go away.


So, finding electricity is a problem. You need batteries, which means battery operated things are again expensive, you have to charge them you have to bring it back all these issues are there, and this one does not have that. But ah as is the rule generally with all these things. The more money you spend, the less information you get, but if you can use less information and smartly, then you can you have to find where your objective is based on it. So this is one other this thing I will just finish up in a minute.


(Refer Slide Time: 14:36)

Ambient Air - Sulphur dioxide

- **Modified West-Gaeke method**
 - Sampling by Impingers placed withdrawing air sample behind the PM_{10} filter in the RDS –
 - 8 hr sampling
 - 1 L/min
 - Absorbing solution – 35 mL of 0.04M Potassium Tetrachloro Mercurate (TCM)
 - Analysis
 - 1 mL of 0.6% sulphamic acid
 - 2 mL of 0.2% formaldehyde solution
 - 2 mL Pararosaniline Solution
 - Dilute with Distilled Water
 - Absorbance with UV Spectrophotometer (Jasco V-530) at 560 nm
 - Measurement of Control and Blank Samples
 - External calibration with Sodium Sulfite

Method Reference :
US EPA Manual Reference Method 40 CFR Part 50, Appendix A






Now, there are various kinds of passive sampling devices, people have worked with a lot of things. This is used in indoor air pollution a lot people use it to find out what is passive smoking in restaurants and bars and all that. So, they have this thing sitting here and there are some standard methods for measurement of the pollutants like Sulphur dioxide and nitrogen oxides.

(Refer Slide Time: 15:01)



So normally the technique that is used for the priority gases, SO_2 , NO_2 , you can impinge and collect it in a solution and measure it as a chemical method for doing it. It is all there in the standard methods. The other option is you have some equipment which does that there is equipment which use UV fluorescence and things like that, ok. So, it is all there in this, just go and read it, I think there is nothing extra that I can.

(Refer Slide Time: 15:28)



So, we have a little bit of balance material remaining in the analysis. So, we are looking at analysis of different species let's just summarize that PM and vapor. So, the organic analysis, this will have something called OC/EC (organic carbon/elemental carbon) this is done using an instrument just call as the OC/EC analyzer. What they do here is similar to the GC for 1 section of this thing.

So, as I mentioned earlier the OC/EC instrument itself works in terms of the OC components, all organic compounds which have some structure some C-H-O-N, the EC component is what is called as elemental carbon. So, this portion can be you can combust it you can oxidize it like the Organic Carbon Analyzer, we talked about long back when we what is called as total organic carbon. So, you combust it and then whatever comes out you measure the CO_2 or CO using infrared instead here what they do is they oxidize it you get carbon dioxide or carbon monoxide.

This is converted back to methane using a reduction reaction. So, this methane can be detected using a flame ionization detector flame as industry as is very sensitive so, and you can use a GC kind of system to without the chromatography. There's no chromatography but what it does is, this is a detector using the GC so, they take the sample of the particulate matter on the filter directly so, you collect a sample on a filter paper.

Take a small amount of the filter paper, small part of this thing and you heat it so you heat to different temperature. some time you heat it at some 100 degrees then you increase it to 200 then

you increase it to 300 and increase it to 400 and increase it to 500. Each temperature you keep it for some time, every time you do this corresponding to this you get a signal in this thing. So, 100 you will get a signal and then you will get some signal in the 200 then you will get some signal in the 300 then you will get some signal in the 400, 500 what this corresponds is the amount.

So, the amount of this red signal indicates the amount of material organic carbon which will come out which will volatilize at that particular temperature. So, you are taking fractions like you have, we don't have any idea of what this chemical specifically is, but we know that this is all constitutes what is constitutes organic carbon 500 degrees it will burn off it will combust there's a car there is just burning off with oxygen.

And it will come out and then it is converted to methane and that methane is measured. So, you can calibrate it by adding a known amount of organic carbon and it is measured in terms of signal for methane then so, the calibration is done like that. Beyond 500 degrees, it is used an optical method is used along at higher temperature goes up 900 degrees centigrade, from 500 to the, see up to less than about 550 degrees centigrade is the organic carbon somewhere around this 550 to about 900 degrees centigrade is the elemental carbon.

Because this doesn't this carbon it will not become carbon dioxide or anything it will stay as it is a soot and this is measured since it is not going to form anything else, it is just another method of measurement which is optical at that high temperature. So, what is reported as the as different fractions of organic carbon and different fractions of elemental carbon, you know all elemental carbon can be clubbed in one group?

And so, people use this data OC/EC ratio of organic or elemental carbon to look at where the source could be. So, if the elemental carbon is high the source is very likely to be from combustion, diesel combustion and all that which forms soot carbon elemental carbon, some commercial sources are very specifically they form soot. So, you know that the if the OCC ratio is different in different places you will know that possibly the source contributing to air pollution and that area is coming from this source.

So, now based on profiles of various sources you can get information regarding or you see source contribution which sources contributing to air pollution in that given area. This is one instrument which is a very specialized instrument. So, here because this filter paper is directly put into the instrument and it has to withstand temperatures of up to 1000 degrees, this filter we use quartz filter paper. In the so, we had mentioned in the previous class that we use quartz, teflon, nylon different materials. The quartz is specifically used for the organic carbon elemental carbon analysis.